



Visual Analysis for Extremely Large-Scale Scientific Computing

# **Evaluation Event**

USE CASE 2: Discrete Element Simulation (DEM) Simulation Tool & Discrete2Continuum (D2C): iFX



# Table of Contents

1	1 iFX Installation Guide			3
			wnload and installation of iFX	
	1.2	Со	nnect to EDDIE Cluster	3
2	Use	er in	nstructions and brief tasks description	5
	2.1	Flu	idized Bed Model Description	6
	2.2	Ra	7	
	2.3	Ta	sk 1: Use Case DEM.M1-01 & M1-02	8
	2.3	.1	Motivation	8
	2.3	.2	Specification	8
	2.4	Ta	sk 2: Use case DEM.M1-03	13
	2.4	.1	Motivation	13
	2.4	.2	Specification	13
	2.5	Ta	sk 4: Use case DEM.M1-05 and DEM.M1-07	14
	2.5	.1	Motivation	14
	2.5	.2	Specification	14
	2.6	Ta	sk 4: Use case DEM.M2-01 and DEM.M2-02	16
	2.6	.1	Motivation	16
	2.6	.2	Specification	16
3	Qu	esti	onnaire for participants	18







# 1 iFX Installation Guide

# **1.1** Download and installation of iFX

- Download current package from: <u>https://cloud.igd.fraunhofer.de/owncloud/public.php?service=files&t=2917f73876454</u> <u>6efd7adb29e8b1061c6</u>
- Unzip downloaded package.
- Directory structure should look like this :

📊 app	11/14/2016 6:07 PM	File folder	
醇 Discrete To Continuum_StepByStep.pptx	11/2/2016 3:47 PM	Microsoft PowerP	2,957 KB
💿 iFX-Velassco.bat	2/3/2016 3:43 AM	Windows Batch File	1 KB
🔊 Start_VELaSSCo_Eddie.bat	1/29/2016 4:37 PM	Shortcut	2 KB
Tutorial-iFX-Velassco.docx	2/3/2016 5:20 AM	Microsoft Word D	2,941 KB
🔃 VELaSSCo-iFX-VisualizationClient-Manua	2/3/2016 10:37 PM	Microsoft PowerP	2,321 KB
🔃 VisualizeParticles.pptx	11/2/2016 4:14 PM	Microsoft PowerP	1,242 KB

# **1.2 Connect to EDDIE Cluster**

- The usernames created for the Evaluation Event to connect to the VPN network are **velgst2** to **velgst50** (the first 9 have only 7 characters).
- Each one has an initial/registration EASE password set to "VELaSSCo". This will have to be changed through the EASE webpage (<u>https://www.ease.ed.ac.uk/</u>).
- Setup VPN connection to EDDIE cluster following the instructions provided in the URL: <u>http://www.ed.ac.uk/information-services/computing/desktop-</u> personal/vpn/vpn-service-using
- Once connected to VPN, to login in into VELaSCCo platform, following provided information will be required:







- Multi-user connection:
  - Username: velassco (default)
  - Password: --- (default)
  - VELaSSCo host: velassco-cluster01-ext.ecdf.ed.ac.uk
  - Port: provided individually by mail. Please check the invitation mail.
- Tunnel through:
  - Tunnel host: velassco-cluster01-ext.ecdf.ed.ac.uk
  - Local Port: same value that Port.
  - Username: provided individually by mail. Please check the invitation mail.
  - Password: provided individually by mail. Please check the invitation mail.

Next, the tunnel should be set up and started:

• Open the *tunneling.bat* file in iFX VELaSSCo Client's folder, and set the proper port for VELaSSCo platform:

🔀 Tun	neling.bat - Visual Studio Code	;	×
File Edi	it View Go Help		
ı م	Tunneling.bat ×	ශි 🗖	
U' 1	<pre>1 putty -N velassco-cluster01-ext.ecdf.ed.ac.uk -L localhost:26267:localhost 26627</pre>		

• Execute *tunneling.bat*. It will request for the credentials to connect to the VELaSSCo platform. Use the provided user name and password to establish the port tunneling.









# 2 User instructions and brief tasks description

Thank you for your participation in this study. You will carry out the tasks on your own in the presence of a facilitator. The facilitator will be giving hints, asking questions, observing your responses to the exercises and supporting you during the whole process. The study will comprise a series of tasks, to be completed one at a time; i.e. once the facilitator, who would be observing your interactions, agrees that you have concluded one task, you will be presented another one.

The study is about the use of VELaSCCo Platform by means of GiD or IFX visualizations clients to operate with a FEM or DEM simulation previously calculated and injected into the Platform. You will be asked to carry out tasks that involve simple simulations actions on the client side.

During the session you have the following tools at your disposal:

- VELaSSCo Open Platform
- **iFX Client V.8.4** (Visualization Tool)
- Text editor and viewer (e.g. Notepad, Word,...)
- Web browser

Your work may be monitored and at the end you will be asked to fill in a simple questionnaire. This will help us understand how people use VELaSCCo Platform and Visualization Clients, how efficient and effective is the VELaSCCo Platform, etc.








# 2.1 Fluidized Bed Model Description

Fluidized bed processes are very common in pharmaceutical and chemical industries. The Fluidized Bed model selected has the following settings:

- ~ 12,000 particles per time-step
- ~ 3,000 contacts (p2p and p2w) per time-step.
- 48,000 time-steps.
- Particle results: mass, volume, velocity vector
- Contact results: Force vector.










# 2.2 Rail Embankment Model Description

Simulations with a high frequency output that cover long time durations are difficult to deal with on a desktop machine due to the large quantity of data generated. The rail embankment model selected has the following settings:

- 207,440 particles per time-step
- ~ 560,000 contacts (p2p and p2w) per time-step.
- 9,102 time-steps 100Hz output.
- Particle results: mass, volume, velocity vector, angular velocity vector
- Contact results: Force vector.



This results in a total data file size of approximately 540 GB generated by the DEM solver.








# 2.3 Task 1: Use Case DEM.M1-01 & M1-02

#### 2.3.1 Motivation

Connect to the VELaSSCo platform and visualise the particle assembly in the visualisation client. Get a result on a particle; concretely get the velocity value specifying a concrete particle id and time-step.

## 2.3.2 Specification

• Execute the iFX velassco client:



- Connect to VELaSCCo Server using iFX:
  - Credentials:
    - Tunnel one of the local ports to the query manager port of VELaSSCo platform that you have received by email.
    - Now that the port tunneling is established, click on the login button in the visualization client:

	-		×
	/ELaSSCo Platform connection Login Login Logia		₽×
Front	Select Data         Provides remote access to the VELaS           Model ID:         None             Analysis ID:         None	SCo platfo	orm.
	Time step: 0.00	•	>







• Press login again in the opened dialog to establish connection between visualization client and VELaSSCo platform:

VELaSSCo Platform Login		-		×	
Server URL: User name: Password:	on For Extremely Large	nost:26267	ific Com		Local port tunneled to th VELaSSCo platform's por

#### • Open a simulation model

• Select Fluidized Bed Large model (FluidizedBed\_large)


ELaSSCo & ×	VELaSSCo & X	VELaSSCo 🗗
Platform connection	Platform connection	Platform connection
Login Logout	Login Logout	Login Logout
Select Data	Select Data	Select Data
Model ID: None	Model ID: FluidizedBed_large	Model ID: FluidizedBed_large
VELASCO_HouseBacTest_part Analysis IDFuldese@Meth_20 Fuldese@BetMeth_20 FuldeseBetMetMetMetMetMetMetMetMetMetMetMetMetMe	Analysis D: None	Analysis ID: DEM
Time steg Barcelona, fullmodel_sm_100M_asci Barcelona, fullmodel_sm_370M_asci fne_mesh-asci	Time step: 0.00	Time step: 2,939,000.00
Mesh ID: None 💌	Mesh ID: None 💌	Mesh ID: None Provides remote access to the VELaSSCo platform
Static Mesh ID: None	Static Mesh ID: None	Static Mesh ID: None
Result ID: None	Result ID: None	Result ID: None
Show Mesh	Show Mesh	Show Mesh
Show Static Mesh	Show Static Mesh	Show Static Mesh
Show Skin	Show Skin	Show Skin
-		Lander Search
esult Queries 5 ×	Result Queries 8 ×	Result Queries de
Ds:	IDs:	IDs:
Show Values	Show Values	Show Values
Show Next 5 Timesteps Graph 1. Select model assoo # ×	Stow Hext 5 Timesteps Graph 2. Select analysis VELASSO 8 X	Show Hext 5 Timesteps Graph 3. Set time step
1. Select model	2. Select analysis	3. Set time step
1. Select model	2. Select analysis VELASCO & * Plaform connection Logon Logout	3. Set time step VELASSCO 5 Platform connection Logon Logout
1. Select model	2. Select analysis VELASCO & * × Platform connection Logn Lognut select Data	3. Set time step
1. Select model	2. Select analysis VELaSSCO & * Platform connection Login Logiut Select Data Model ID: RudatedBed Jarge ·	3. Set time step
1. Select model	2. Select analysis VELASCO & * × Platform connection Logn Lognut select Data	3. Set time step
1. Select model	2. Select analysis VELaSSCO & * Platform connection Login Logiut Select Data Model ID: RudatedBed Jarge ·	3. Set time step
1. Select model  SSCs   * *	2. Select analysis VELASCO ** Platform connection Select Data Mode ID: Fluideedleed_large *	3. Set time step
1. Select model asso ** tation connection logon logout bode ID Fuidcadded Jarge * merket Dat Three steps: 2,239,000.00 ten ID Inter- ten tation ** ten tation	2. Select analysis Platom connection Select Data Mode ID: Fladdeedlergie Analysis ID: [DEM Time step: 2,299,000.00	3. Set time step Platform connection Lugar Logant Select Data Model D: FluidleetBed Jarge Analysis D: BBM Time step: [2,939,000.00]
1. Select model  ssco **  tetom connection  elect Data elect Data mayris ID: DEM  time step: 2,999,000.00  time step: 2,999,000.00  time step: 2,099,000.00  time step: 2,099,000 time step: 2,090,00 time step: 2,099,000 time step: 2,090,00 time step: 2,099,000 tim	2. Select analysis Platform connection Logout Select Data Model D: PladaceBed Jarge Model D: PladaceBed Jarge Tme step: 2,939,000.00 Control Control Co	3. Set time step Netsoco Platom Logot Select Data Model D: FuldesBed Jarge Analyse DD: DEM Tme step: [2,939,000.00 Meth ID: particles
1. Select model  ssco **  tetom connection  elect Data elect Data mayris ID: DEM  time step: 2,999,000.00  time step: 2,999,000.00  time step: 2,099,000.00  time step: 2,099,000 time step: 2,090,00 time step: 2,099,000 time step: 2,090,00 time step: 2,099,000 tim	2. Select analysis Platform connection Login Logint Select Dat Mode ID: Fladdeedleed levinge • Time step: 2,999,000.00 • • Time step: 2,999,000.00 • •	3. Set time step
1. Select model ssco	2. Select analysis VELOSCO  VELOSCO V	3. Set time step Platform connection Logout Select Data Model Di: Fluidsestiend Jarge Time step: (2,999,000.00 Mecht ID: particles State: Mecht ID: None Result ID: Velocity (1990)
1. Select model asso ** tation connection topin Logau topin Logau	2. Select analysis Platform connection Login Logint Select Dat Mode ID: Pladdeedleed levinge • Time step: 2,999,000.00 • • Time step: 2,999,000.00 • •	3. Set time step VEASCO O Plifore concetto Logan Logan Select Data Model D: FliddeeBed Jarge Analysis D: DBM Time step: (2,939,000.00 Mesh D: [prifide Readt D: [None Readt D: [None Readt D: [None Readt D: [None
A. Select model asco	2. Select analysis	3. Set time step Set to a Set to a Set to a Meth D: performer Result D: Velocity
A. Select model asso	2. Select analysis Putorn conection Logout Select Data Model D: Fuddeeddeed gerge Web ID: [DEM Web ID: [DEM	S. Set time step Netrone connector Select Data Medi D: FindinesBed Jarge   Medi D: FindinesBed Jarge  Medi D: Select Data Medi D: Select Di Se
A. Select model asso	2. Select analysis Platform connection Login Logint Select Dat Model D: Fladdredded (proge	3. Set time step Platom concton Logont Select Data Medi D: Platom Set Medi Time step: [,939,000,00 ] ]
A. Select model assc	2. Select analysis Putorn conection Logout Select Data Model D: Fuddeeddeed gerge Web ID: [DEM Web ID: [DEM	S. Set time step Netrone connector Select Data Medi D: FindinesBed Jarge   Medi D: FindinesBed Jarge  Medi D: Select Data Medi D: Select Di Se








• Reset the viewport



- Visualize a contour fill of a particle result.
  - Visualize the velocity-Y in the skin of the particles in selected time step




- Rotate the model
- Now, the color mapping can be modified by dragging the color mapping min, max, or center. The color mapping can also changed by double right clicking on it.










- Visualizing multiple timesteps of particles as animation
  - o Open Particle Animation dialog



o Switch to the Particle Animation tab

	Show Static Mesh	
	Show Skin	
VELaSSCo	Particle Animation Query	
Result Queries		₽×
IDs:		







• Set the parameters as follows:

	Particle Animation Query	8	×	
Duration of animation in seconds	Duration: 20.0			
Number of frames to be queried	Num Frames: 10 skip: 1	•	╉	Number of frames to skip in between
	Get data		]	
Animation time slider	•			
	Start			

- Press Get Data.
- Press **Play** to see the animaton.

**<u>Note</u>**: Don't logout, because the following use case is also using this model.






# 2.4 Task 2: Use case DEM.M1-03

#### 2.4.1 Motivation

Get the evolution of a result on a particle over time; for instance, get the velocity ycomponent value for all simulation time-steps of specific particle id.

## 2.4.2 Specification

- Get the evolution of a result on a particle over time.
  - Get the particle number 2724's evolution of velocity y-component value for next five time steps:
    - Enter the particle IDs, select vy, and press Show Next 50 time steps.
    - The results should look like the following figure:



## Velocity








# 2.5 Task 4: Use case DEM.M1-05 and DEM.M1-07

## 2.5.1 Motivation

Compute Discrete to Continuum (d2c) values of the model, get the result in a specific node of the d2c Mesh, and visualize the contour fill of a discrete2continuum result.

## 2.5.2 Specification

- Compute d2c of the model
  - Open Discrete to Continuum Dialogue (Similar to Particle Animation dialog).
  - Set the dialog parameters as follows:
    - Static mesh = D2C\_FluidizedBed\_small
    - D2C analysis name = user initials + "\_D2C\_FB"
    - Time-step options = INTERVAL
    - List of time-steps = 2799000,6799001
    - Coarse-graining method = Gaussian
    - Coarse-graining options:
      - Width = 0.0024
      - Cut-off factor = 3
    - Process contacts = True
    - Do temporal averaging = True
      - Temporal Averaging options = ALL
      - DeltaT = 30000
  - Now, the calculated mesh is stored in the database.
- Visualize a contour fill of a result
  - User: Visualize the contour fill of velocity-Y in the skin of the volume mesh of the computed d2c (model "D2C\_Mesh" and analysis name "user initials + "\_d2c\_FB"") for time step 4799000.5












- $\circ$   $\;$  Reset the view and set the color mapped component to  $\mbox{Velocity-Y}$
- $\circ$   $\;$  Play with color map, to get the result shown in the figure.



- Get the result in a specific node of the d2c mesh
  - User: Open D2C\_Mesh model
  - User: *Get the Bulk density value for:* 
    - Analysis = user initials + "\_d2c\_FB"
    - Time-step **# 4799000.5**
    - Result = Density
    - Node number **300, 1000**











## 2.6 Task 4: Use case DEM.M2-01 and DEM.M2-02

#### 2.6.1 Motivation

Compute temporally averaged Discrete to Continuum (d2c) values of the model, get the result in a specific node of the d2c Mesh and visualize the contour fill of a discrete2continuum result.

#### 2.6.2 Specification

• Select Rail Embankment model (RailEmbankment\_100TimeSteps)

VELaSSCo				8	×
Platform	connection				
	Login	Lo	ogout		
Select Da	ta				
Model ID:	None		-		
Analysis IC	DEM_Box EmbankmentAnalysis FullEmbankment_70kmph_10 VELaSSCo_HbaseBasicTest_ FluidisedBedMesh_2D FluidisedBed_small		^		
Time step	RailEmbankment_100Timeste FullEmbankment_70kmph_10 FluidizedBed_large fine_mesh-ascii_		~	)	

- Compute d2c of the model by opening Discrete2Cointinuum query dialog and entering the following parameters:
  - Static mesh = NewEmbankmentTest\_0\_1m\_77K
  - D2C analysis name = user initials
     + " D2C RAIL"
  - Time-step options = INTERVAL
  - $\circ$  List of time-steps = 0.2, 1
  - Coarse-graining method = Gaussian
  - *Coarse-graining options:* 
    - Width = 0.09
    - Cut-off factor = 3
  - Process contacts = True
  - Do temporal averaging = True
  - Temporal averaging options = ALL
  - *DeltaT = 30000*


₽× Discrete to Continuum Query • Static Mesh ID: NewEmbankmentTest 0 1m 77K Analysis Name: Mory\_D2C\_RAIL Time Steps: INTERVAL -Time Steps Value: 0.2,1 Coarse Gaining Method: Gaussian Coarse Gaining Width: 0.09 Coarse Gaining Cut-off: 3 Process Contacts  $\checkmark$ Temporal Averaging  $\checkmark$ Temporal Average Options: ALL • DeltaT: 30000 Spatial Integral Integral Dimensions: 1D Integral Direction: X Compute

- Visualize a contour fill of a result
  - User: Visualize the contour fill of Bulk Density in the volume mesh of the computed d2c (model "D2C\_Mesh" and analysis name "user initials + "\_d2c\_FB"") for temporarily averaged time step 0.595.










- Get the result in a specific node of the d2c mesh
  - User: Open D2C\_Mesh model (NewEmbankmentTest\_0\_1m\_77K)
    - User: Get the Contact stress value for:
      - Analysis = user initials + "\_d2c\_RAIL"
      - Time-step **# 0.595**
      - Result = Contact stress
      - Node number **30000, 10120**









# **3** Questionnaire for participants

Measuring the quality of a service can be a very difficult exercise. Unlike product where there are specific specifications such as length, depth, width, weight, colour etc. a service can have numerous intangible or qualitative specifications. In addition there is there expectation of the customer with regards the service, which can vary considerably based on a range of factors such as prior experience, personal needs and what other people may have told them.

The questionnaire below is in three sections. On the one hand the first section asks you to rank all software tools for pre and post processing of numerical simulations in science and engineering according to your expectations i.e. what you expect all these tools to provide. On the other hand the second section asks you to rank the iFX's VELaSSCo visualization client according to your experiences and perceptions. The third section asks you about the overall satisfaction of iFX's VELaSSCo visualization client.

**Expectations** deals with your opinions of software tools for pre and post processing of numerical simulations. What we are interested in here is a number that best shows you expectations about software tools for pre and post processing of numerical simulations offering services.

**Perceptions** relate to your feelings about the iFX's VELaSSCo visualization client. Please show the extent to which you believe this tool has the feature described in the statement. Here, we are interested in a number from 1 to 7 that shows your perceptions about the iFX's VELaSSCo visualization client.

You should rank each statement following a seven-point Likert-style scale from 1=very unimportant to 7=very important

The questionnaire is available in the following URL to be filled:

https://docs.google.com/forms/d/e/1FAIpQLScEQWrvk07eriIBNCb2xhjpeizZyYTtyQ WEHbNE3SgbX6WgwA/viewform#responses

In summary, our purpose is to get your valuable feedback about your experience with the VELASSCO Platform and its usability against expectations.

We would also appreciate your impressions on practical issues and any other comment or criticisms that you may find interesting.

Please send your completed questionnaires telematics using the URL indicated above.

Thanks for your time.

The VELASSCO project.



